

Tutorial
Creation of GES files



access

This presentation

Group A	Group B	Topics
15:45-16:00	08:45-09:00	Registration
16:00-16:30	09:00-09:30	8a Coupling to thermodynamics Plenary – G/S <ul style="list-style-type: none">• Thermo-Calc equilibrium and Scheil-Calculation as a basis for MICRESS simulations• Creating a GES5 thermodynamic database with Thermo-Calc
16:30-17:15	09:30-10:15	8b Coupling to thermodynamics Hands on <ul style="list-style-type: none">• Add a further alloy element to the T001_DeltaGamma example• Create an own Fe-C-Cr-Mn system• Include your own GES5 file• (Re-)Assign elements and phases



Some useful considerations

- Before setting-up a MICRESS simulation for a new alloy system:

■ Get a feeling for what you are doing!

- What is a suitable domain size?
 - ➔ Might symmetries be exploited to minimize computational effort?
- What are the initial and boundary conditions?
- What is the alloy system of interest?
 - ➔ Which elements have to be considered?
 - ➔ May some elements be neglected?
- Which phases are to be expected?
 - ➔ during solidification?
 - ➔ during heat-treatment?
- Perform some thermodynamic calculations to learn more....

Get a feeling for relevant temperatures




Amount Mole percent

Fe 98.0

C 1


Mn 1

```
# Initial volume of (thickness) phase 2 (FCC_A1): [cm]
8.0000
# Temperature at which the initial equilibrium
# will be calculated? [K]
1786.000
#
#
# Initial concentrations
# =====
# How shall initial concentrations be set?
```





access

Perform a Scheil Calculation




**ShortCut to
Scheil Module**

A Scheil Calculation Result



TCFe10



TCFe6

Coupling to Thermodynamic (& Mobility) Data

**GES files are needed for
TQ coupled simulations**

```
# Phase diagram - input data
# =====
# Is a thermodynamic database to be used?
# Options: database no_database
database
#
# Name of Thermo-Calc *.GES5 file without extension?
#
GES_Files/Steel
#
```

} switch on-off TC coupling

} name of GES5-file

```
# Frequency for complete relinearization [s] =
1.
#
# A description of each pairwise thermodynamic
# interaction has to be specified.
#
# Input of the phase diagram of phase 0 and phase 1:
# -----
# Which phase diagram is to be used?
# Options: database linear
database
# Maximal allowed local temperature deviation [K]
-1.
```

} complete relinearisation period

} switch between TC coupling and
linearized phase diagram
for each phase interaction

} maximum effective temperature deviation (-1: off)

Allocating the phases in the database to the phases in MICRESS

```
#-----  
# The database contains the following components:  
# 1: C  
# 2: FE  
# 3: MN  
# Specify relation between component indices Micress -> TC!  
# The main component has in MICRESS the index 0  
# Thermo-Calc index of (MICRESS) component 0?  
2  
# Thermo-Calc index of (MICRESS) component 1?  
1  
# Thermo-Calc index of (MICRESS) component 2?  
3  
# 0 -> FE  
# 1 -> C  
# 2 -> MN  
# The database contains 4 phases:  
# 1: LIQUID  
# 2: BCC_A2  
# 3: CEMENTITE  
# 4: FCC_A1  
# Specify relation between phase indices Micress -> TC!  
# The matrix phase has in MICRESS the index 0  
# Thermo-Calc index of the (MICRESS) phase 0?  
1  
# Thermo-Calc index of the (MICRESS) phase 1?  
2  
# Thermo-Calc index of the (MICRESS) phase 2?  
4  
# 0 -> LIQUID  
# 1 -> BCC_A2  
# 2 -> FCC_A1
```

element 1,2,3 in database

component numbers

phases1, 2, 3, 4 in database

phase numbers

Need for another ges5 file

- The number of **phases** in MICRESS
may be less or equal the number of phases in the ges5 file
- The number of **chemical elements** in MICRESS
must be equal the number of elements in the ges5 file










A new ges file thus is needed if

- a desired element is not contained in the actual ges5 file
- an element in the actual ges file shall not be considered
- a desired phase is not listed in the actual ges5 file

Use Template for ges file creation

MICRESS_6_100 ▶ Examples ▶ ↻ Examples durchsuchen

Brennen Neuer Ordner ☰ 📁


Name	Änderungsdatum	Typ
 Grain_Growth_Microstructure.txt	27.06.2013 09:29	Textdokument
 Grain_Growth_Pinning_Pres_dri.txt	27.06.2013 09:29	Textdokument
 Grain_Growth_Profile_Mue11.txt	27.06.2013 09:29	Textdokument
 Grain_Growth_Profiles_dri.txt	27.06.2013 09:29	Textdokument
 Grain_Growth_Solute_Drag_dG_dri.txt	27.06.2013 09:29	Textdokument
 Grain_Growth_Solute_Drag_dri.txt	27.06.2013 09:29	Textdokument
 HOWTO_FeCMn.TCM	27.06.2013 09:29	TCM
 korn_T950.vtk	27.06.2013 09:29	VTK
 P Peak 1D dri.txt	27.06.2013 09:29	Textdokument

***ThermoCalc Macro file
as template for the
generation of .ges5
files for MICRESS***

detailed description of the „HowToFeCMn_ges_file“ Macro template

@@ lets see what we are doing:
set-echo
@@select thermodynamic database
go dat
@@for example TCFE6 iron and steel database
sw TCFE6
@@define elements in alloy systems
d-sys fe c mn
@@list the system
l-sy CONSTITUENT
l-sy phases
@@define phases of interest
@@first reject all phases
*rej phases **
@@then restore phases of interest
@@e.g. fcc liquid and bcc
rest phases liq fcc bcc
@@get defined system into Ges Workspace
get
@@append mobility database
app mob2

@@define elements in alloy systems (same as above!!)
d-sys fe c mn
@@list the system
l-sy CONSTITUENT
l-sy phases
@@define phases of interest
@@first reject all phases
*rej phases **
@@then restore phases of interest for diffusion
@@(and modelled in database!)e.g. fcc and bcc:
rest phases fcc bcc
@@get defined/appended system into Ges Workspace
get
@@ goto Gibbs Workspace
go gibbs
@@ save Gibbs Workspace to file (here: FeCMn.ges)
save FeCMn



on-line demo

Next : Hands-on

Group A	Group B	Topics
15:45-16:00	08:45-09:00	Registration
16:00-16:30	09:00-09:30	8a Coupling to thermodynamics Plenary – G/S <ul style="list-style-type: none">• Thermo-Calc equilibrium and Scheil-Calculation as a basis for MICRESS simulations• Creating a GES5 thermodynamic database with Thermo-Calc
16:30-17:15	09:30-10:15	8b Coupling to thermodynamics Hands on <ul style="list-style-type: none">• Add a further alloy element to the T001_DeltaGamma example• Create an own Fe-C-Cr-Mn system• Include your own GES5 file• (Re-)Assign elements and phases

Create your first simple ges5 file

- Copy „HowToFeCMn“ macro to „MyGESFile“
- Edit MyGesFile
- Switch to TCFE database
- Switch to mobFe database
- Add element Chromium Cr
- leave phases unchanged
- Name output FeCMnCr
- Run MyGESFile macro using ThermoCalc
- Copy created ges file to ges file directory
- Run the modified DeltaGamma Example